

Now that we have been introduced to Maxwell's Equations on the previous two pages, we can attempt to solve them. Textbooks on classical electrodynamics (e.g., Jackson (1962), Griffiths (1981), Bohren and Huffman (1983)) take a general approach of assuming little and letting Maxwell's equations force upon you conclusions about what functional forms of solutions are possible for propagating waves. This is not a physics text, so I will propose a form for propagating electric and magnetic fields and show that they satisfy Maxwell's equations. That approach is sufficient to show with a minimum of math and physics how waves can propagate in dielectrics like water. In so doing, we will discover the relation between the absorption coefficient and the imaginary parts of the index of refraction and the wave number. The discussion of plane waves on this page sets the stage for a deeper investigation of wave propagation on the next two pages, which are on dispersion.

Plane Waves in a Dielectric

Other than electromagnetic waves propagating in a vacuum, the simplest solution of Maxwell's equations for wave propagation is for a plane wave in a dielectric material. The term "plane wave" refers to an electromagnetic wave (i.e., light) that is propagating in some direction, and which has the same properties at all points of a plane perpendicular to the direction of propagation. As will be seen, if we know the electric field of the wave, we can find the magnetic field from Maxwell's equations (or vice versa). Thus it is customary to consider only the electric field of the wave.

Consider first an electromagnetic wave propagating in a vacuum. We are free to choose a convenient coordinate system, so let the wave propagate in the $+\hat{x}$ direction, and let the electric field \mathbf{E} oscillate in the $\pm\hat{y}$ direction (i.e., the electric field is linearly polarized in the y direction). The associated magnetic field then oscillates in the $\pm\hat{z}$ direction. This situation is illustrated in Fig. figure1.




Figure 1: Illustration of sinusoidal electric and magnetic plane waves in a vacuum. The red arrows represent the electric field and the blue arrows are the magnetic field.

We can write the magnitude of the electric field as

$$E(x, t) = E_o \cos(\kappa'x - \omega t + \phi) , \quad (1)$$

where E_o sets the magnitude of the electric field, $\kappa' = 2\pi/\lambda$ is the angular wave number, and $\omega = 2\pi/T$ is the angular frequency; λ is the wavelength and T is the period of the oscillation. For propagation in a vacuum, $\lambda = cT$; i.e., a wave propagating at the speed of light c travels a distance λ in one period of the oscillation. It is common to use k rather than κ' for the wavenumber; the reason for my choice of κ' will be explained below.

Electric fields, wave numbers, frequencies, and the like are of course real quantities. However, it will prove to be convenient to write the electric field of Eq. (equation1) as the real part of a complex quantity:

$$E(x, t) = \Re\{E_o \exp i(\kappa'x - \omega t + \phi)\},$$

where $\Re\{\dots\}$ stands for the real part of the argument, and we recall that $e^{i\theta} = \cos\theta + i\sin\theta$ where $i = \sqrt{-1}$. Some authors use a subscript c to indicate a complex field, and some use a tilde, and some leave it to the reader to figure out from the context which variables are real and which are complex. I will use a tilde and write

$$\begin{aligned} \tilde{E}(x, t) &= \&E_o \exp i(\kappa'x - \omega t + \phi) \\ &= \&\tilde{E}_o \exp i(\kappa'x - \omega t) \end{aligned} \quad (2)$$

In the second equation, the phase angle has been incorporated into the amplitude so that $\tilde{E}_o = E_o \exp(i\phi)$. Now $E = \Re\{\tilde{E}\}$, and so on. It is customary to omit writing the \Re symbol, in which case it is understood that at the end of any calculation involving complex numbers we must take the real part to get back to a real physical quantity. Some authors call \tilde{E} the “complex electric field”, but a better terminology is to say that \tilde{E} is the complex *representation* of the real electric field E .

We can rewrite (align2) as

$$\tilde{E}(x, t) = \tilde{E}_o \exp i\kappa'(x - \frac{\omega}{\kappa'}t).$$

It is easily shown by substitution that any function of the form $f[s(x - vt)]$, where s is a constant scale factor, satisfies the 1D wave equation

$$\frac{\partial^2 f(x, t)}{\partial x^2} = \frac{1}{v^2} \frac{\partial^2 f(x, t)}{\partial t^2}.$$

Thus any function of the form $f[s(x - vt)]$ describes a function with shape $f(sx)$ at time $t = 0$ propagating in the $+x$ direction with speed v . We can thus identify the speed

$$v_p = \frac{\omega}{\kappa'} \quad (3)$$

as the speed of the electromagnetic wave. This speed is known as the *phase speed* of the sinusoidal wave because it shows how fast a point with a given phase of the sinusoidal wave, say the wave crest, travels.

A function of the form $\tilde{E}_o \exp i(\kappa'x - \omega t)$ propagates with an amplitude \tilde{E}_o that is independent of time and location. That is correct for propagation in a vacuum. However, in absorbing matter, the Bouguer-Lambert-Beer law says that the irradiance attenuates exponentially with distance according to $\exp(-ax)$, where a is the absorption coefficient. We can

build this attenuation into the electric field in an ad hoc manner by replacing the constant amplitude of the electric field with a function of x with the form

$$\tilde{E}_o \leftarrow \tilde{E}_o \exp(-\kappa''x),$$

where κ'' is a positive constant. (The \leftarrow means “is replaced by”.) Equation (align2) is then replaced by

$$\begin{aligned} \tilde{E}(x, t) &= \&\tilde{E}_o \exp(-\kappa''x) \exp i(\kappa'x - \omega t)\} \\ &= \&\tilde{E}_o \exp i[(\kappa' + i\kappa'')x - \omega t] = \tilde{E}_o \exp i(\kappa x - \omega t). \end{aligned} \quad (4)$$

Here $\kappa = \kappa' + i\kappa''$ is called the *complex wave number*. I will omit writing $\tilde{\kappa}$ since there is no ambiguity with another usage for κ .

Before proceeding, we must face a problem of notation. On the water IOPs page, I wrote the complex index of refraction as $m = n + ik$, where n was the real index of refraction and k was called the imaginary part of the index of refraction. It is also common to use k as the wavenumber: $k = 2\pi/\lambda$. Every author seems to have a slightly different way to avoid using the same k symbol for two different quantities. Bohren and Huffman (1983) use a Roman k for the complex wavenumber, which they write as $k = k' + ik''$, and they use an italic k for the imaginary part of the index of refraction. They also use N rather than m for the complex index of refraction. Thus my $m = n + ik$ is Bohren and Huffman’s $N = n + ik$. Griffiths (1981) uses κ_+ for the real part of the complex wavenumber and κ_- for the complex part. Thus he writes the complex wavenumber as $\kappa = \kappa_+ + i\kappa_-$. Mishchenko et al. (2002) write $k = k_R + ik_I$ and $m = m_R + im_I$. For this page and the next, I have chosen to use k for the imaginary part of the index of refraction and κ for the wavenumber, with a single prime on the real part and a double prime on the imaginary part. You will similarly see the complex index of refraction written as $n = n' + in''$. To further complicate matters, some authors write the time dependence in Eq. (equation1) as $+\omega t$, in which case the complex index of refraction (in my notation) becomes $m = n - ik$ and the complex wavenumber is $\kappa = \kappa' - i\kappa''$. The whole notation business is a mess, and you just have to figure out each author’s preferences.

Now let us turn the electric and magnetic fields into vectors so we can insert them into Maxwell’s equations. In Fig. figure1 the electric field oscillates in the y plane, and the magnetic field lies in the z plane. So for these fields we can write

$$\tilde{\mathbf{E}}(x, t) = \tilde{E}_o \exp i(\kappa x - \omega t) \hat{\mathbf{y}} \quad (5)$$

$$\tilde{\mathbf{B}}(x, t) = \tilde{B}_o \exp i(\kappa x - \omega t) \hat{\mathbf{z}} \quad (6)$$

At this point I have proposed two traveling waves for the electric and magnetic fields. Now we can ask, “under what conditions do waves of the form of Eqs. (align5) and (align6) satisfy Maxwell’s equations?”

Recall that Maxwell's equations in matter are

$$\nabla \cdot \mathbf{D} = \&\rho_f \quad (7)$$

$$\nabla \cdot \mathbf{B} = \&0 \quad (8)$$

$$\nabla \times \mathbf{E} = \& - \frac{\partial \mathbf{B}}{\partial t} \quad (9)$$

$$\nabla \times \mathbf{H} = \&\mathbf{J}_f + \frac{\partial \mathbf{D}}{\partial t} \quad (10)$$

with the constitutive relations

$$\mathbf{D} = \&\epsilon_o \mathbf{E} + \mathbf{P} \quad (11)$$

$$\mathbf{H} = \& \frac{1}{\mu_o} \mathbf{B} - \mathbf{M}. \quad (12)$$

For a linear medium, \mathbf{P} is proportional to \mathbf{E} and is commonly written $\mathbf{P} = \epsilon_o \chi \mathbf{E}$, where χ is the electric susceptibility (i.e., χ measures how susceptible the material is to being polarized by an electric field). χ is assumed to be independent of \mathbf{E} and is independent of location and direction in a homogeneous, isotropic medium. Thus $\mathbf{D} = \epsilon_o(1 + \chi)\mathbf{E}$. The quantity $\epsilon = \epsilon_o(1 + \chi)$ is the permittivity of the medium. If we assume that there are no free electric charges in the medium ($\rho_f = 0$), the first of Maxwell's equations (Eq. align7) is $\nabla \cdot \mathbf{D} = 0$. Inserting the complex representation $\tilde{\mathbf{D}} = \epsilon \tilde{\mathbf{E}}$ into $\nabla \cdot \tilde{\mathbf{D}}$ gives

$$\begin{aligned} \nabla \cdot \tilde{\mathbf{D}} &= \left\{ \frac{\partial}{\partial x} \hat{\mathbf{x}} + \frac{\partial}{\partial y} \hat{\mathbf{y}} + \frac{\partial}{\partial z} \hat{\mathbf{z}} \right\} \cdot \epsilon \tilde{E}_o \exp i(\kappa x - \omega t) \hat{\mathbf{y}} \\ &= \epsilon \left[i\kappa \tilde{E}_o \exp i(\kappa x - \omega t) \hat{\mathbf{x}} \cdot \hat{\mathbf{y}} + 0 + 0 \right] = 0 \end{aligned}$$

after noting that $\hat{\mathbf{x}} \cdot \hat{\mathbf{y}} = 0$ and that the y and z derivatives are 0 because the wave varies only in x . Thus the form of Eq. (align5) for $\tilde{\mathbf{E}}(x, t)$ satisfies $\nabla \cdot \tilde{\mathbf{D}} = 0$. Likewise, the form of Eq. (align6) for $\tilde{\mathbf{B}}(x, t)$ satisfies $\nabla \cdot \tilde{\mathbf{B}} = 0$.

Next insert the proposed $\tilde{\mathbf{E}}(x, t)$ and $\tilde{\mathbf{B}}(x, t)$ into Eq. (align9). The result is

$$i\kappa \tilde{E}_o \exp i(\kappa x - \omega t) \hat{\mathbf{z}} = i\omega \tilde{B}_o \exp i(\kappa x - \omega t) \hat{\mathbf{z}}$$

This equation is satisfied only if

$$\tilde{B}_o = \frac{\kappa}{\omega} \tilde{E}_o. \quad (13)$$

Thus, *given the electric field, we can compute the magnetic field.* Taking the real parts of this equation gives

$$B_o = \frac{\kappa'}{\omega} E_o = \frac{1}{v_p} E_o = \frac{n}{c} E_o \quad (14)$$

after recalling the definition of the phase speed from Eq. (equation3), and recalling that the speed of light in a medium with real index of refraction n is the speed in vacuo divided by n .

For a dielectric, the magnetization \mathbf{M} is zero, so $\mathbf{H} = \frac{1}{\mu} \mathbf{B}$, where μ is the permeability of the medium. (In general one can write $\mu = \mu_o(1 + \chi_m)$, where χ_m is the magnetic

susceptibility of the medium. In a dielectric, μ is very nearly equal to μ_o , the permeability of a vacuum.) If there are no free currents ($\mathbf{J}_f = 0$), the remaining Maxwell equation align10 reduces to

$$\nabla \times \frac{1}{\mu} \mathbf{B} = \frac{\partial}{\partial t} \epsilon \mathbf{E}$$

Inserting the complex representations into this equation gives

$$-i \frac{\kappa}{\mu} \tilde{B}_o \hat{\mathbf{y}} = -i \omega \epsilon \tilde{E}_o \hat{\mathbf{y}}$$

or

$$\tilde{B}_o = \frac{\omega}{\kappa} \mu \epsilon \tilde{E}_o$$

This result combined with that of Eq. (equation13) implies that

$$\kappa^2 = \omega^2 \mu \epsilon$$

or

$$\kappa = \omega \sqrt{\mu \epsilon}.$$

When the wave equation is derived starting with Maxwell's equations in matter, the wave speed is $v = 1/\sqrt{\mu \epsilon}$ (rather than $v = c = 1/\sqrt{\mu_o \epsilon_o}$ as was seen in Eq. (10) of the previous page for the vacuum case). The speed of light in a medium with real index of refraction n is c/n . Given that κ in the last equation is complex (which implies that μ and/or ϵ must also be complex, as will be seen in the discussion of dispersion), we can introduce the complex index of refraction $m = n + ik$ and write

$$\kappa = \omega \sqrt{\mu \epsilon} = \frac{\omega m}{c} = \frac{2\pi m}{\lambda}, \quad (15)$$

after recalling that ω/c is the free-space wavenumber $2\pi/\lambda$.

We can now rewrite the complex representation of the electric field as

$$\tilde{\mathbf{E}}(x, t) = \& \tilde{E}_o \exp i \left(\frac{2\pi m x}{\lambda} - \omega t \right) \hat{\mathbf{y}} \quad (16)$$

$$= \& \tilde{E}_o \exp \left(\frac{-2\pi k x}{\lambda} \right) \exp i \left(\frac{2\pi n x}{\lambda} - \omega t \right) \hat{\mathbf{y}}, \quad (17)$$

Taking the real part gets us back to the real electric field:

$$\mathbf{E}(x, t) = E_o \exp \left(\frac{-2\pi k x}{\lambda} \right) \cos \left(\frac{2\pi n x}{\lambda} - \omega t + \phi \right) \hat{\mathbf{y}}. \quad (18)$$

The corresponding equation for $\tilde{\mathbf{B}}$ is

$$\mathbf{B}(x, t) = \frac{1}{v_p} E_o \exp \left(\frac{-2\pi k x}{\lambda} \right) \cos \left(\frac{2\pi n x}{\lambda} - \omega t + \phi \right) \hat{\mathbf{z}}, \quad (19)$$

or an equivalent based on Eq. (equation14).

We have now shown that sinusoidal plane waves can propagate through a dielectric provided that the magnitude of the magnetic field is proportional to the magnitude of the electric field according to Eq. (equation14), and that the wave number is related to the angular frequency according to Eq. (equation15).

The Absorption Coefficient

The equations above are for electric and magnetic fields, which are what physicists like to play with. Oceanographers, however, almost always work with irradiance. For the moment, let \mathcal{E} be irradiance, rather than the usual E , to avoid confusion with the electric field.

The Poynting vector is defined by

$$\mathbf{S} = \frac{1}{\mu} \mathbf{E} \times \mathbf{B} .$$

This vector points in the direction of wave propagation, and it has units of $\text{Js}^{-1}\text{m}^{-2}$, i.e. of irradiance. The Poynting vector thus describes the irradiance of the propagating electromagnetic wave in the medium. Inserting \mathbf{E} and \mathbf{B} from Eqs. (equation18) and (equation19) gives

$$\mathbf{S}(x, t) = \sqrt{\frac{\epsilon}{\mu}} E_o^2 \exp\left(\frac{-4\pi kx}{\lambda}\right) \cos^2\left(\frac{2\pi nx}{\lambda} - \omega t + \phi\right) \hat{\mathbf{x}} ,$$

after using Eq. (equation14), $v = 1/\sqrt{\mu\epsilon}$, and $\hat{\mathbf{y}} \times \hat{\mathbf{z}} = \hat{\mathbf{x}}$. This is the instantaneous irradiance of the wave at time t , which cannot be measured by an instrument at optical frequencies of order 10^{14} Hz. What is measured is the time-average of $\mathbf{S}(x, t)$ over many wave cycles. Recalling that the average of the cosine squared over a wave period is $1/2$ gives

$$\mathcal{E}(x) = \langle \mathbf{S}(x) \rangle = \frac{1}{2} \sqrt{\frac{\epsilon}{\mu}} E_o^2 \exp\left(\frac{-4\pi kx}{\lambda}\right) \hat{\mathbf{x}} .$$

The thing to note in this equation is that the irradiance is proportional to the square of the electric field amplitude, and that its magnitude it damps out exponentially as

$$\mathcal{E}(x) = \mathcal{E}(0) \exp\left(\frac{-4\pi kx}{\lambda}\right) = \mathcal{E}(0) \exp(-ax) .$$

This is the Bouguer-Lambert-Beer law as derived from Maxwell's equations. In the last equation we have identified the usual absorption coefficient a as

$$a = \frac{4\pi k}{\lambda} . \tag{20}$$

You will also see the absorption coefficient written as

$$a = 2\kappa'' , \tag{21}$$

which follows from Eq. (align4).

Generalizations

I have made a number of simplifications in the preceding development, which must be noted for completeness.

I assumed that the electric field was in the $\hat{\mathbf{y}}$ plane and the magnetic field was in the $\hat{\mathbf{z}}$ plane, and that both were perpendicular to to the direction of propagation and to each

other. In a more general treatment, you find that Maxwell's equations can be satisfied only if \mathbf{E} and \mathbf{B} are perpendicular to the direction of propagation, i.e., electromagnetic waves are transverse waves. Furthermore, a vacuum or in a homogeneous, isotropic, linear medium like water or glass, \mathbf{E} and \mathbf{B} are also perpendicular to each other. (A linear medium means that \mathbf{D} and \mathbf{H} are proportional to \mathbf{E} and \mathbf{B} , respectively.) The choice of \mathbf{E} in the $\hat{\mathbf{y}}$ plane was arbitrary. In general, you can write

$$\tilde{\mathbf{E}} = \tilde{\mathbf{E}}_0 \exp i(\boldsymbol{\kappa} \cdot \mathbf{x} - \omega t),$$

where \mathbf{x} and $\boldsymbol{\kappa}$ are arbitrary directions in space, and the direction of the electric field is contained in the amplitude vector $\tilde{\mathbf{E}}_0$. It is then found that

$$\boldsymbol{\kappa} \cdot \tilde{\mathbf{E}}_0 = \boldsymbol{\kappa} \cdot \tilde{\mathbf{B}}_0 = \tilde{\mathbf{E}}_0 \cdot \tilde{\mathbf{B}}_0 = 0.$$

That is, these three vectors are mutually perpendicular. The magnetic field can then be written as

$$\tilde{\mathbf{B}} = \frac{1}{v_p} \boldsymbol{\kappa} \times \tilde{\mathbf{E}}$$

My example was just a special case of these equations with $\boldsymbol{\kappa} = \kappa \hat{\mathbf{x}}$ and $\mathbf{x} = \hat{\mathbf{x}}$.

The electric and magnetic fields are perpendicular for plane waves propagating in a dielectric. However, they are not always perpendicular, for example in the 3D fields created by scattering by a particle or radiated by an antenna. Similarly, although the electric and magnetic fields are in phase in a dielectric, they are out of phase by as much as 45 deg in a conducting medium. When decomposing electric and magnetic fields using Fourier transforms, the \mathbf{E} and \mathbf{B} fields of each Fourier mode are orthogonal, however the total fields resulting from a sum of modes may not be orthogonal. That is to say, if \mathbf{E}_1 and \mathbf{B}_1 are orthogonal (i.e., $\mathbf{E}_1 \cdot \mathbf{B}_1 = 0$), and \mathbf{E}_2 and \mathbf{B}_2 are orthogonal, it does not follow that $(\mathbf{E}_1 + \mathbf{E}_2) \cdot (\mathbf{B}_1 + \mathbf{B}_2) = 0$.

The complex representation of the Poynting vector is

$$\tilde{\mathbf{S}} = \frac{1}{\mu} \tilde{\mathbf{E}} \times \tilde{\mathbf{B}} = \tilde{\mathbf{E}} \times \tilde{\mathbf{H}}.$$

To get back to the real version, the formula is

$$\mathbf{S} = \Re\{\tilde{\mathbf{E}}\} \times \Re\{\tilde{\mathbf{H}}\} = \Re\{\tilde{\mathbf{E}} \times \tilde{\mathbf{H}}^*\},$$

where $\tilde{\mathbf{H}}^*$ is the complex conjugate of $\tilde{\mathbf{H}}$. Note that these formulas are not the same as $\Re\{\tilde{\mathbf{E}} \times \tilde{\mathbf{H}}\}$.